




Exporting a Text File with X-PAD Ultimate




Start X-PAD Ultimate and Select your Job.



Select Export & Share



Select Text File (ASCII)



In Parameters Screen

Data = All Points

Scheme = PN-NEX-C (USA)

Separator = Comma (,)

File Extension = .txt

Select Next

Fields

- ☒ Point name
- ☒ North Coordinate (N)
- ☒ East Coordinate (E)
- ☒ Elevation (Z)
- ☐ Latitude WGS84
- ☐ Longitude WGS84
- ☐ Ellipsoid height WGS84
- ☐ ECEF WGS84 X
- ☐ ECEF WGS84 Y
- ☐ ECEF WGS84 Z
- ☒ Code
- ☐ Description

Next

Fields Screen

Select Point Name

Select North Coordinate (N)

Select East Coordinate (E)

Select Elevation (Z)

Select Code

Select Next


Preview

Name	North/N	East/E	El
610	1890106.754	579420.874	
609	1890106.754	579420.874	
608	1890125.288	579411.254	
607	1890125.288	579411.254	
606	1890139.856	579406.870	
605	1890094.408	579402.603	
604	1890094.408	579402.603	
603	1890119.212	579402.391	
602	1890120.141	579401.585	
601	1890117.155	579399.078	
600	1890117.155	579399.078	
599	1890125.108	579398.482	
598	1890129.368	579395.751	
597	1890128.492	579390.742	
596	1890110.879	579390.079	

Accept


You will now see a preview of the points you have selected for Export.

Select Accept



You will now see a Report Screen with the number of Exported Points you have selected.

Select Accept




On the Export & Share Screen you will now be given the options of locations for your Exported Points.


In this example I have chosen to save my text file to the Device/Cloud.

Select Accept


Downloading a Text File to your Computer




Using a Cable (USB to USB-C) connect your device to your computer.




In this example I am using a Mesa 3 tablet so I will navigate to Mesa / Internal Storage.




I will now be taken to the Folder Location on my device. I will now select the X-PAD Folder.



In the X-PAD Folder I will now see my Site Folders. Open your Site Folder or My Site Folder if you have not chosen to create a new site with each project.



Once you have opened your Site Folder select the Export Folder.



You will now see your Exported Text Files where you can Copy or Cut the files from your Device and Paste into your specific Storage Area (File) on your Computer